Fuelwood Monitoring on Wilderness Campsites

Site Number: ______ Date: ______Name: _____

Center ring: 0-5 meters	Count of pieces			Diameter & Length, each piece		
Transect #	Fine (< ½") [2 m]	Small (½ - 1") [3 m]	Medium (1-3") [5 m]	Large (>3") [5 m]		
1	[2 III]		(1 <i>5)</i> [<i>5</i> m]	· ·		
2						
3						
4						
5						
6						
	!					
Middle ring: 5- 10 meters		Count of pieces	S	Diameter & Length each piece		
Transect #	Fine (< ½") [2 m]	Small (½ - 1") [3 m]	Medium (1-3") [5 m]	Large (>3") [5 m]		
1			1			
2						
3	-					
4						
5			THE REPORT OF THE PROPERTY OF			
6						
			I			
Outer ring: 10-15 meters	Count of pieces			Diameter & Length each piece		
Transect #	Fine (< 1/2")	Small (½ -	Medium	Large (>3")		
1	[2 m]	1") [3 m]	(1-·3'") [5 m]	[5 m]		
2		Proposition of the state of the				
3						
4						
5		_				
6						

Distance to first 10 pieces between 1 and 3" diameter and >30 cm in length. (Six transects, spaced at 60-degree intervals, 1.5 meters wide).

l		
.9	· t	2.
·ş	.٤	.1

Control

				9
				ς
				au
				٤
				7
		· · · · · · · · · · · · · · · · · · ·		I
Large (>3")	Medium [5 m]	- ½') [sm2 [m £] ("[Fine (< ½") [2 m]	Transect#
Diameter & Length each piece		Center ring: 0-5 meters		

Notes:

Instructions for monitoring fuels:

- 1. Find the centerpoint of the site, preferably a place where you can create a 15 m radius circle that doesn't go in the water or in the rocks.
- 2. Assess the "inner ring"
 - Randomly select six transect bearings.
 - Measure fuels along each transect beginning at the center point, according to the worksheet. The transect is a vertical "plane" -eount wood that is suspended above the ground. Count only dead material.
 - Fine fuels over first 2 m
 - Small fuels over first 3 m
 - Medium and large fuels over full 5 m
 - Diameter and length of each piece of large material
- 3. Assess the "middle ring"
 - Randomly select six transect bearings.
 - Beginning at 5 meters (and extending to 10 meters), repeat process of measures
- 4. Assess the "outer ring"
 - Randomly select six transect bearings.
 - Beginning at 10 meters (and extending to 15 meters), repeat process of measures
- 5. Measure the distance to the first 10 pieces of material of fire-appropriate size (1-3")
 - Select a random transect and create 6 evenly-spaced transects
 - Pace out to the point at which your transect (armspan width) crosses 10 pieces of wood of the desired size.
- 6. Identify a control area
 - Select a place outside the gathering range of any campsites.
 - The site should be as similar as possible to the campsite, in terms of overstory, vegetation, and topography.
 - Measure wood within a 5 meter circle (as for the inner ring on the campsite).
 - Measure the distance to the first 10 pieces of wood as for the campsite.

Problems/issues:

- Natural variability (forest pockets) in subalpine areas.
- Is it important to compute volumes?
- Can be time consuming if you count fine fues.